



These views are optimized for desktop/laptops





all climbing grades start with the number 5. the grades can range from 5.0 to 5.14, however once the grade reaches 5.10, letter begin to be added. it goes up to 5.15, but for our purposes, The scale can look like this:

5.5
5.6
5.7
5.8
5.9
5.10a
5.10b
5.10c
5.10d
5.11a
5.11b
5.11c
5.11d
5.12a
5.12b
5.12c
5.12d
5.13
5.13+

The App will use only the mantissa portion of the rating:

- For example, the rating of '5.7' will be represented by, and used in averaging calculations as just '7'
- Letter ratings will stand for the following: {a: 0, b: 25, c: 50, d: 75}
- So, 5.11d will be represented by, and be used in averaging calculations as '11.75'
- 5.13+ will be represented by, and be used in averaging calculations as '14'

for averaging out the value, 5.10a can be a value of 10, 5.10b can be a value of 10.25, 10c can be 10.5, 10d 10.75 and a similar pattern for 5.11 and 5.12

GYM OWNER ACCESS

ADD ROUTES

EDIT ROUTES

DELETE ROUTES

HEAD:

GYM NAME

GYM COLLECTION NAME

LOGIN:

USERNAME

PASSWORD

BODY:

ROUTE 1

ROUTE 2

ROUTE 3

ADMIN ACCESS

ADD GYM OWN ACCOUNTS

DELETE GYM OWNER ACCOUNTS

ADD ADMIN ACCESS ACCOUNTS

ADMIN COLLECTION

ADMIN LOGIN:

USERNAME

PASSWORD

ADMIN LOGIN:

USERNAME

PASSWORD

USER ACCESS

CLIMBZOMBIE.COM

RATE A ROUTE

CHOOSE GYM

CHOOSE ROUTE

- SEE SETTER GRADE
- SEE AVERAGE CLIMBER GRADE
- SAY WHICH ONE THEY AGREE WITH
- IF NEITHER SET NEW GRADE
- RATE ROUTE

ADMIN DASH

LIST OF GYM ACCOUNTS

ADD GYM ACCOUNT

DELETE GYM ACCOUNTS

GYM OWNER DASH

ROUTE DETAILS

EDIT

DEL

ROUTE DETAILS

EDIT

DEL

ROUTE DETAILS

EDIT

DEL

ADD GYM ACCOUNT DASH

- GYM NAME,
- NUMBER OF ROUTES TO INIT
- PASSWORD
- CONFIRM PASSWORD

CREATE

BACK TO ADMIN DASH

DELETE GYM DASH

LIST OF ALL GYMS
(CLICK ON GYM BUTTON TO DELETE)

BACK TO ADMIN DASH